

August 14 & 15, 2013



TELEDYNE INSTRUMENTS

QUIKLOOK

QUIKLOOK

QUIKLOOK

QUIKLOOK

QUIKLOOK



MidasWL

MOV Integrated Design Analysis System WEAK LINK Software

Principal Engineer Richard A. Enos

MidasWL Analysis Software - Features

- Software is an Engineering Tool
- Software use is controlled by the Utility
- Software is Appendix B − QA Software
- Software is User Friendly
- Software User Manual documents required analysis inputs for individual component configurations
- Software is customized to use Site Specific Design Acceptance Criteria and Material Properties

MidasWL - New Items Added in 2013

- User Input Material Properties Capability
- 3D-SRSS(XYZ) Seismic Analysis Capability
- Gate Valve Stem Pinned Link Evaluation
- Actuator Adapter Plate Bolts Evaluation
- Bonnet Neck and Valve Neck Gusset/Ribs
- Butterfly HBC Adapter Plate Bolts Eval
- Butterfly Yoke Leg Evaluations
- Butterfly Yoke Bolting Evaluation
- Butterfly Yoke Weld Evaluations

MidasWL Analysis Software - Structure




Table 1: Listing of MIDASWL Components Versus Valve Type

Midas Weak Link		Component	Valve Type						
Primary Tab	Secondary Tab	Sub Type	Gate	Globe	Globe1	Butterfly	Ball	N/A	
Disc	Disc	Plug, (Globe Disc)		Х	х	C 0.0000	1/4		
		Solid Wedge	х				80 0		
		Flexible Wedge	х						
		Split Wedge	х	9	K	8	\$4 B		
		Flat Plate Wedge	Х				/A .		
		Butterfly Disc - Symmetrical				Х	56 - 5		
		Butterfly Disc - Non Symmetrical		9		х	60 - 0	(
		Anchor Darling Double Disc	Х						
	Disc/Stem Connection	Disc / Stem Threaded Connection	X	Х	х		20 0		
		Disc / Stem T-Head Connection	Х				100		
		Link - Pin Connection	Х	9	c .		60 8	ć.	
		Disc Lifter		Х	х				
		Disc / Stem Lifter with Retaining Nut		Х	х	î	20 3	-	
	Disc Arm	Disc Arm Evaluation	Х				500		
Bonnet	Valve Bonnet Neck	Valve Bonnet Neck Evaluation	Х	Х	Х	ė.	90 8	į.	
		Valve Bonnet Neck (Ellipse)	Х	Х	х				
		Valve Bonnet Neck (Rectangular)	X	Х	х	i	20 0	-	
	Bonnet/Valve Conn	Bonnet to Body Bolt Evaluation	Х	Х	х		100		
		Bonnet to Body Bolt (Ellipse)	Х	Х	Х		85 5		
		Bonnet to Body Bolt (Rectangular)	х	Х	х				
		Body / Bonnet Retaining Ring Evaluation	х	Х	Х	82	90		
Stem	Stem	Stem Evaluation	Х	Х	х		20 0		
		Shaft / Pin / Keyway Evaluation				х	Х	i	
		Stem w Undercut	х	Х	х				
		Stem w Keyway	Х	Х	х	i	E .		
		Stem w Undercut & Keyway	Х	Х	х		100 E		
	Stem Nut	Stem Nut Eval (SMB-000 to 4)	Х	Х	х		60 8		
		Stem Nut Eval (SMB-5)	Х	Х	х				
	Torque Arm	Torque Arm Evaluation	х	Х			100		


Table 1: <u>Listing of MIDASWL Components Versus Valve Type</u> (Cont'd)

Midas Weak Link		Component	Valve Type						
Primary Tab	Secondary Tab	Sub Type	Gate	Globe	Globe1	Butterfly	Ball	N/A	
Actuator	Operator Bolts	Operator Bolt Evaluation	Х	Х	Х			4	
	Adapter Plate Bolts	Adapter Plate Bolt Evaluation	Х	Х	Х	Х	Х	á	
	HBC Bolts	HBC Bolt Evaluation				х	х		
	Valve Body Neck	Valve Body Neck Evaluation	Х	Х	Х		5	1	
Valve Body		Valve Body Neck (Ellipse)	Х	Х	Х				
		Valve Body Neck (Rectangular)	Х	Х	Х		8	ě	
	Body/Bonnet Flange	Body / Bonnet Flange Evaluation	Х	Х	Х				
		Body / Bonnet Flange (Ellipse)	Х	Х	Х			j	
		Body / Bonnet Flange (Rectangular)	Х	Х	Х			1 45	
	Yoke Leg	Rectangular Yoke Leg	Х	Х	Х	Х	Х	á	
		Ribbed Yoke Leg - Inside	Х	Х	Х				
		Ribbed Yoke Leg - Outside	Х	Х	Х			j	
		Circular Yoke Leg	Х	Х	Х	Х	Х	0	
	Yoke / Bonn Conn	Circular Yoke Bolt Evaluation	Х	Х	Х	х	Х		
		Yoke Slab Flange Bolts	Х	Х	Х		8	ñ.	
Yoke		Yoke Slab Flange Bolts w/ Stiffening Effect	Х	Х	Х			2	
		Yoke / Bonnet Threaded Connection	Х	Х	Х			2	
		Yoke / Bonnet Circular Weld	х	Х	Х	х	х		
		Yoke / Bonnet Partial Circular Weld	Х	Х	Х	х	х	j J	
		Yoke / Bonnet Rectangular Weld	Х	Х	Х	х	х	1 6	
		Yoke Retainer Clamp	Х	Х	Х			ē.	
		Yoke Breech Lock	Х	Х	Х				
	Yoke Flange	Circular Lower Yoke Flange	Х	Х	Х			e:	
		Yoke Slab Flange	Х	Х	Х			2	
		Yoke Slab Flange w/ Stiffening Effect	х	Х	Х				


MidasWL - Input Data Panels

- Design Data Valve, Actuator & Motor Data
- General Data Temperatures & Seismic Data
 [2D-AbsSum(XY&YZ), 3D-SRSS(XYZ)]
- Disc Configuration Data
- Bonnet Configuration Data
- Actuator Bolting Configuration Data
- Stem Configuration Data
- Valve Body Configuration Data
- Yoke Configuration Data


MidasWL - Calculations Main panel




MidasWL - Disc panel




MidasWL - Disc/Stem Connection panel




MidasWL - Disc Arm panel




MidasWL - Valve Bonnet Neck panel




MidasWL - Bonnet/Valve Connection panel




MidasWL - Operator Bolts panel




MidasWL - Adapter Plate Bolts panel




MidasWL - HBC Bolts panel




MidasWL - Stem panel




MidasWL - Stem Nut panel




MidasWL - Torque Arm panel




MidasWL - Valve Body Neck panel




MidasWL - Body/Bonnet Flange panel




MidasWL - Yoke Leg panel




MidasWL - Yoke / Bonnet Connection panel



MidasWL - Yoke Flange panel



MidasWL - Output panel



MidasWL – Electronic Sign-off Capability

The check command is provided to facilitate an electronic review/check of the changes made to the MIDASWL calculations. By clicking on FILE \ CHECK \ CALCULATION, the user may electronically approve the calculation changes made by another user. This command is only available to privileged users other than the Preparer.

MidasWL - Reports

- Reverse References
- History
- Main Report (Full WL Analysis Report)
- Data Sheet
 - Inputs & Results Grouped
 - Inputs & Results Sorted



Questions?

